


We've all been here.

Select connection from the tool bar and then to configure the TN3270.  
Ensure check marks are in Auto Connect and Auto Disconnect.



The image shows a 'Connection Configuration' dialog box with a title bar containing a question mark and a close button. The 'General' tab is selected, and the connection name 'TN3270' is shown in the tab header. The 'Auto Connection Options' section contains three checkboxes: 'Auto Connect' (checked), 'Exit On Disconnect' (unchecked), and 'Auto Disconnect' (checked). The 'Installed Interfaces' section shows a list with 'TN3270' selected and 'Demo Host' below it, with a 'Properties' button to the right. The 'Host Character Set Information' section has 'Language' set to 'English' and 'Code Page' set to '037' with a dropdown arrow. At the bottom are 'OK', 'Cancel', and 'Connect' buttons.

Connection Configuration

General | TN3270

Auto Connection Options

- ☒ Auto Connect
- ☐ Exit On Disconnect
- ☒ Auto Disconnect

Installed Interfaces

- TN3270
- Demo Host

Properties


Host Character Set Information

Language: English


Code Page: 037

OK Cancel Connect


Configure the following as usual.




Save printer profile to a unique profile name. Save profile and close, returning to the “RUMBA Mainframe Printer” window.



Select tools, then services




Install your printer profile that you named earlier.



This is good!




Remove the check mark from "PC Printer Queues. Because RUMBA instructions says so!




Quit and Save.. But your not done yet... At this point you may need to open the rumba printer session to adjust your fonts, page size and double check your printer destination..

Go to Control panel select Administrative Tools then select Services..






Find and Select your rumba printer..






Right click, Select properties, change “Startup type” to Automatic..



Click the “Log On” tab

Remove Check mark out of “Allow service to interact with desktop”.



Close and accept settings. Reboot computer and without logging, go to a different computer and change your L-Term printer destination to the rumba printer and send it a G0-81 print product..

Good Luck.. ....d.w...